Email Setup for Mozilla Thunderbird

Follow the steps listed below to configure Mozilla Thunderbird email client.

<u>Step 1</u>

Open Mozilla Thunderbird. If you are setting up for the first time, skip the initial wizard.

<u>Step 2</u>

Click on Tools menu and then Account Settings.



<u>Step 3</u>

Click on Account Actions on bottom right and then Add Mail Account.

| | Mail Accoun | t Setup | × |
|---|--|--------------------------|-----------------|
| Your <u>n</u> ame: Emai <u>l</u> address: Password: | DreamSoft- Test test@dreamsoftindia.com | Your name, as shown to o | thers |
| <u>-</u> assiroidi | ✓ Remember password | | |
| | | | |
| | | | |
| | | | |
| | | | |
| | | | |
| <u>G</u> et a new acco | ount | Continue | C <u>a</u> ncel |
| | | | |

Step 4

Enter Your name, Email Address, Password and click Continue.

<u>Step 5</u>

Choose between IMAP and POP3.

Step 6

Click Manual config.

<u>Step 7</u>

Enter Server hostname as mail.yourdomain.com for both Incoming and Outgoing servers. (If your domain name is testdomain.net, then you would put mail.testdomain.net).

<u>Step 8</u>

If you are configuring POP3, Incoming Port should be 110. If you are configuring IMAP, Incoming Port should be 143. Outgoing SMTP Port should be 587.

<u>Step 9</u>

Set the SSL to None for both Incoming and Outgoing servers.

<u>Step 10</u>

Set the Authentication to Normal Password for both Incoming and Outgoing servers.

<u>Step 11</u>

Click Create Account button and the OK button.

| Your name: | DreamSof | t- Test Your name, as | shown to oth | iers | | | |
|---|-------------------------|--|-----------------------|----------------------------------|-------------|---|-----|
| Emai <u>l</u> address: | test@drea | amsoftindia.com | | | | | |
| Password: | ••••• | •• | | | | | |
| | Remer | mber password | | | | | |
| | | | | | | | |
| | | | | | | | |
| | 000 | Server hostname | Port | SSL | | Authentication | |
| Incoming: P | OP3 v | Server hostname mail.dreamsoftindia.com | Port 110 V | SSL None | ~ | Authentication Normal password | • |
| Incoming: P Outgoing: SM | OP3 ↓ MTP | Server hostname mail.dreamsoftindia.com mail.dreamsoftindia.com | Port 110 V 25 V | SSL None None | > | Authentication Normal password | · · |
| Incoming: Pe Outgoing: SN Username: Inc | OP3 V MTP coming: | Server hostname mail.dreamsoftindia.com mail.dreamsoftindia.com test-dreamsoftindia | Port 110 V 25 V | SSL None Nutgoing: | > | Authentication Normal password Normal password test-dreamsoftindia | ~ |
| Incoming: Pr Outgoing: SN Username: Inc | OP3 ¥ MTP coming: | Server hostname mail.dreamsoftindia.com mail.dreamsoftindia.com test-dreamsoftindia | Port 110 V 25 V | SSL None None Outgoing: | v | Authentication Normal password Normal password test-dreamsoftindia | ~ |
| Incoming: Pr Outgoing: SN Username: Inc | OP3 V MTP coming: | Server hostname mail.dreamsoftindia.com mail.dreamsoftindia.com test-dreamsoftindia | Port 110 v 25 v | SSL None None Outgoing: | * | Authentication Normal password Normal password test-dreamsoftindia | ~ |