Email Setup for Outlook 2010

Follow the steps listed below to configure Microsoft Outlook 2010 email client.

<u>Step 1</u>

Open Microsoft Outlook 2010.

<u>Step 2</u>

Click on File and then Add Account.



<u>Step 3</u>

On the New Account screen, click the Manually configure server settings radio button and click Next.



<u>Step 4</u>

Select Internet E-mail and click Next.



<u>Step 7</u>

Enter your name and email address in User Information.

<u>Step 8</u>

Select Account Type as POP3 or IMAP.

<u>Step 9</u>

In the Incoming mail server field enter mail.yourdomain.com In the Outgoing mail (SMTP) field enter mail.yourdomain.com (If your domain name is testdomain.net, then you would put mail.testdomain.net).

Step 10

Enter your user name and password in Logon Information.

User Information		Test Account Settings
Your Name:	Test DreamSoft	After filling out the information on this screen,
E-mail Address:	test@dreamsoftindia.com	button below. (Requires network connection)
Server Information		
Account Type:	POP3	Test Account Settings
Incoming mail server:	mail.dreamsoftindia.com	
Outgoing mail server (SMTP):	mail.dreamsoftindia.com	
Logon Information		
User Name:	test-mail.dreamsoftindia	
Password:	********	
	Remember password	

<u>Step 11</u>

Click More Settings.

<u>Step 12</u>

Click on Outgoing Server.

<u>Step 13</u>

Select the My outgoing server (SMTP) requires authentication checkbox. Make sure that Use same settings as my incoming mail server is selected and then click OK.

Internet E-mail Settings	×
General Outgoing Server Connection Advanced	
Wy outgoing server (SMTP) requires authentication	
Our contract of the sector	
Cog on using	
User Name:	
Password:	i I
Remember password	
Require Secure Password Authentication (SPA)	
Log on to incoming mail server before sending mail	
OK Cancel	

<u>Step 14</u>

Click the Advanced tab at the top.

<u>Step 15</u>

Use the following type of encrypted connection should be selected as NONE.

<u>Step 16</u>

Set Outgoing mail server port to 25 or 2525 or 587.

<u>Step 17</u>

Click OK button.

General	
	Outgoing Server Connection Advanced
Server	Port Numbers
Incom	ning server (POP3): 110 Use Defaults
	This server requires an encrypted connection (SSL)
Outgo	ping server (SMTP): 25
U	se the following type of encrypted connection: None
Server	Timeouts
Short	Long 1 minute
Delivery	у —
V Le	ave a copy of messages on the server
	Remove from server after 15 🚔 days
	Remove from server when deleted from 'Deleted Items'
	OK Cancel