

## Email Setup for Windows Live


Follow the steps listed below to configure Windows Live email client.

### Step 1

Open Windows Live Mail.

### Step 2

Click on [Accounts](#) and then [Email](#).



### Step 3

Enter your [Email Address](#), [Password](#) and [Display Name](#).

### Step 4

Tick [Manually configure server settings](#) checkbox and click [Next](#).

Windows Live Mail

## Add your email accounts

Email address:  
someone@example.com  
[Get a Windows Live email address](#)

Password:

Remember this password

Display name for your sent messages:  
Example: John Doe

Make this my default email account  
 Manually configure server settings

Most email accounts work with Windows Live Mail including  
Hotmail  
Gmail  
and many others.

Cancel Next

### Step 7

In [Incoming server information](#), select [Server Type](#) as POP or IMAP.

### Step 8

In the [Server address](#) field enter mail.yourdomain.com  
(If your domain name is testdomain.net, then you would put mail.testdomain.net).

### Step 9

If you are configuring Server type as POP, Port should be 110.  
If you are configuring Server type as IMAP, Port should be 143.

The screenshot shows the 'Configure server settings' dialog box in Windows Live Mail. It is divided into two main sections: 'Incoming server information' and 'Outgoing server information'. In the 'Incoming server information' section, the 'Server type' is set to 'POP', the 'Server address' is 'pop.123-reg.co.uk', the 'Port' is '110', and 'Authenticate using' is set to 'Clear text'. The 'Logon user name' is 'mark@123-reg-support.co.uk'. In the 'Outgoing server information' section, the 'Server address' is 'smtp.123-reg.co.uk' and the 'Port' is '25'. There are two checkboxes: 'Requires a secure connection (SSL)' which is unchecked, and 'Requires authentication' which is checked. At the bottom right, there are three buttons: 'Cancel', 'Back', and 'Next'.

#### Step 10

Select [Authenticate using](#) as [Clear Text](#).

#### Step 11

Enter your mailbox username in [Logon user name](#).

#### Step 12

In the [Outgoing server information](#), add [Server address](#) as mail.yourdomain.com  
(If your domain name is testdomain.net, then you would put mail.testdomain.net).

#### Step 13


[Port](#) should be 25 or 25 or 587.

#### Step 14

Tick [Requires Authentication](#) checkbox.

### Step 15

Click [Next](#) button and the [Finish](#) button.



The screenshot shows the 'Configure server settings' dialog box in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is 'Configure server settings' with a subtitle: 'If you don't know your email server settings, contact your ISP or network administrator.' The dialog is divided into two columns: 'Incoming server information' and 'Outgoing server information'. In the 'Incoming server information' section, the 'Server type' is set to 'POP', the 'Server address' is 'pop.123-reg.co.uk', the 'Port' is '110', and 'Requires a secure connection (SSL)' is unchecked. The 'Authenticate using' dropdown is set to 'Clear text', and the 'Logon user name' is 'mark@123-reg-support.co.uk'. In the 'Outgoing server information' section, the 'Server address' is 'smtp.123-reg.co.uk', the 'Port' is '25', 'Requires a secure connection (SSL)' is unchecked, and 'Requires authentication' is checked. At the bottom right, there are three buttons: 'Cancel', 'Back', and 'Next'. The 'Next' button is highlighted with a red border.

### Step 15

Click [Next](#) button and the [Finish](#) button.

## Your email account was added

✓ mark@123-reg-support.co.uk was added

[Add another email account](#)

Finish